

Dr. Cohen

Gloves: 7-blue latex free indicator / 7 - latex free

Procedure: Breast Reduction

Position: Supine, arms out and secured with 2 kerlix on each side, lower body bair hugger, SCD boots

Prep: Chloraprep if allergy will use betadine, careful not to rub off surgical site markings

Draping:

Universal drape

Will use:

Skin stapler

4 blue towels

loban strip cut into fourths

Medications:

30cc 0.5% marcaine with epinephrine

Saline irrigation

Equipment:

2- ESU machines with smoke evacuators at foot of bed – Settings: 30/30

1-Bair hugger

1- Scale to weigh specimen

Supplies:

2 -Smoke evac bovie pencils

2- Teflon protected bovie tips

2- bovie grounding pads

4- 10 blades

4-marking pens

2- rulers

2-25g needles

2-10cc syringes

2-aspeto

1-Basin for irrigation

38, 42 and 45 cookie cutter

Lap pads only no raytec sponges on field

*if specimen >900g will use 15F round drain with 2-0 nylon on PS-2

Sutures:

2-0 vicryl SH X 1

3-0 monocryl PS-2 x6

4-0 monocryl PS-2 X 6

3 skin staplers

Dressing:

4- Dermabond

*Have prineo available

6 ABD pads and bra

Special Instructions:

** IF oncoplastic reduction WEIGH LUMPECTOMY SPECIMEN PRIOR TO SENDING*

**At end of case please provide patient label and specimen weights on card for Dr. Cohen